

JHSTOX.TXT

```
//JHSTOX PROC
//*****
//** PS005 - IEFBR14 DELETES THE WORK DSNS IN THE LOAD STEP      00098100
//*****                                                       00098700
//** PS005 EXEC PGM=IEFBR14                                         00098800
//IN01   DD DSN=&SYSTPFX..&RQ..SORTED.OPUPDT&OPNO.,          00104100
//          DISP=(MOD,DELETE,DELETE),                                00104301
//          UNIT=SYSDA,
//          SPACE=(TRK,(1,1),RLSE)
//*****
//** SORT OPUPDT FILE ON DT-ROW-UPD
//*****
//PS010  EXEC PGM=SORT,
//          PARM='CORE=MAX,RELEASE=ON,RLSOUT,SECOND=ON'
//SYSOUT  DD SYSOUT=&SYSOUT
//SYSPRINT DD SYSOUT=&SYSOUT
//SORTWK01 DD UNIT=&DISK,
//          SPACE=&SRTEPSRP
//SORTWK02 DD UNIT=&DISK,
//          SPACE=&SRTEPSRP
//SORTWK03 DD UNIT=&DISK,
//          SPACE=&SRTEPSRP
//SORTWK04 DD UNIT=&DISK,
//          SPACE=&SRTEPSRP
//SORTWK05 DD UNIT=&DISK,
//          SPACE=&SRTEPSRP
//SORTWK06 DD UNIT=&DISK,
//          SPACE=&SRTEPSRP
//SORTWK07 DD UNIT=&DISK,
//          SPACE=&SRTEPSRP
//SORTWK08 DD UNIT=&DISK,
//          SPACE=&SRTEPSRP
//SORTWK09 DD UNIT=&DISK,
//          SPACE=&SRTEPSRP
//SORTWK10 DD UNIT=&DISK,
//          SPACE=&SRTEPSRP
//SORTWK11 DD UNIT=&DISK,
//          SPACE=&SRTEPSRP
//SORTWK12 DD UNIT=&DISK,
//          SPACE=&SRTEPSRP
//SORTWK13 DD UNIT=&DISK,
//          SPACE=&SRTEPSRP
//SORTWK14 DD UNIT=&DISK,
//          SPACE=&SRTEPSRP
//SORTWK15 DD UNIT=&DISK,
//          SPACE=&SRTEPSRP
//SORTWK16 DD UNIT=&DISK,
//          SPACE=&SRTEPSRP
//SORTWK17 DD UNIT=&DISK,
//          SPACE=&SRTEPSRP
//SORTWK18 DD UNIT=&DISK,
//          SPACE=&SRTEPSRP
//SORTWK19 DD UNIT=&DISK,
//          SPACE=&SRTEPSRP
//SORTWK20 DD UNIT=&DISK,
//          SPACE=&SRTEPSRP
//**SORTIN  DD DUMMY
//SORTIN   DD DSN=&SYSTPFX..&RQ..OPUPDT.OP&OPNO.(0),
//          DISP=SHR
//SORTOUT  DD DSN=&SYSTPFX..&RQ..SORTED.OPUPDT&OPNO.,
//          DISP=(NEW,CATLG,DELETE),
//          DCB=*.SORTIN,
//          &DVCPUP
//
```

```

JHSTOX.TXT
//SYSIN DD DSN=&LIBPFX..&PH..CNTL(&SROPUP0),
//          DISP=SHR
//***** 00098100
//** PS015 - IEFBR14 DELETES THE WORK DSNS IN THE LOAD STEP 00098700
//***** 00098800
//PS015 EXEC PGM=IEFBR14 00104100
//IN01 DD DSN=&SYSTPFX..&RQ..HSTRPTI&OPNO..DATA, 00104301
//          DISP=(MOD,DELETE,DELETE), 00104701
//          UNIT=SYSDA,
//          SPACE=(TRK,(1,1),RLSE)
//IN02 DD DSN=&SYSTPFX..&RQ..HSTRPT.DATA&OPNO, 00104301
//          DISP=(MOD,DELETE,DELETE), 00104701
//          UNIT=SYSDA,
//          SPACE=(TRK,(1,1),RLSE)
//IN03 DD DSN=&SYSTPFX..&RQ..ARCLMOUT.DATA&OPNO, 00104301
//          DISP=(MOD,DELETE,DELETE), 00104701
//          UNIT=SYSDA,
//          SPACE=(TRK,(1,1),RLSE)
//IN04 DD DSN=&SYSTPFX..&RQ..OP&OPNO.HEDIS.DATA, 00104301
//          DISP=(MOD,DELETE,DELETE), 00104701
//          UNIT=SYSDA,
//          SPACE=(TRK,(1,1),RLSE)
//***** 00098100
//** SBPREHRO -
//***** 00098100
//PS020 EXEC PGM=IKJEFT01,
//          REGION=&SIZE,
//          COND=(0,LT)
//STEPLIB DD DSN=&DB2REG..SDSNLOAD,
//          DISP=SHR
//          DD DSN=&LIBPFX..&PH..LOADLIB,
//          DISP=SHR
//SYSPRINT DD SYSOUT=&SYSOUT
//SYSUDUMP DD SYSOUT=&SYSOUT
//SYSABOUT DD SYSOUT=&SYSOUT
//SYSSDBOUT DD SYSOUT=&SYSOUT
//SYSABEND DD SYSOUT=&SYSOUT
//SYSOUT DD SYSOUT=&SYSOUT
//SYSTSPRT DD SYSOUT=&SYSOUT
//SYSTSIN DD DSN=&LIBPFX..&PH..CNTL(&DB2REG),
//          DISP=SHR
//          DD DSN=&LIBPFX..&PH..CNTL(SBPREHR&OPNO),
//          DISP=SHR
//HRODRIVE DD DSN=&SYSTPFX..&RQ..HSTRPTI&OPNO..DATA,
//          DISP=(NEW,CATLG,DELETE),
//          DCB=(RECFM=FB,LRECL=53,BLKSIZE=0),
//          &DVCHRO
//HSTRPTI DD DSN=&SYSTPFX..&RQ..HSTRPT.DATA&OPNO,
//          DISP=(NEW,CATLG,DELETE),
//          DCB=(RECFM=FB,LRECL=37,BLKSIZE=0),
//          UNIT=&DISK,
//          SPACE=(CYL,(1,1),RLSE)
//ARCLMOUT DD DUMMY
//**RCLMOUT DD DSN=&SYSTPFX..&RQ..ARCLMOUT.DATA&OPNO,
//          DISP=(NEW,CATLG,DELETE),
//          DCB=(RECFM=FB,&ATRIPCLM),
//          &DVCPUPA
//HEDISOUT DD DSN=&SYSTPFX..&RQ..OP&OPNO.HEDIS.DATA,
//          DISP=(NEW,CATLG,DELETE),
//          DCB=(RECFM=FB,&ATRIPCLM),
//          &DVCPUPA
//ERRORLOG DD SYSOUT=&SYSOUT
//***** 00098100

```

JHSTOX.TXT

```

///* PS025 - IEFBR14 DELETES THE SORTOUT DSN          00098700
//*****                                         00098800
//PS025      EXEC PGM=IEFBR14,                      00104100
//           COND=(0,LT)
//IN01       DD   DSN=&SYSTPFX..&RQ..HSTRPTI&OPNO..SDATA,
//               DISP=(MOD,DELETE,DELETE),             00104301
//               UNIT=SYSDA,
//               SPACE=(TRK,(1,1),RLSE)                00104701
//*****                                         00104701
///* SORT HRODRIVER FILE ON DT_ROW_UPD
//*****                                         00104701
//PS030      EXEC PGM=SORT,
//           PARM='CORE=MAX,RELEASE=ON,RLSOUT,SECOND=ON',
//           COND=(0,LT)
//SORTMSG    DD   SYSOUT=&SYSOUT
//SYSOUT     DD   SYSOUT=&SYSOUT
//SORTWK01   DD   UNIT=&DISK,
//               SPACE=&SRTEPSRP
//SORTWK02   DD   UNIT=&DISK,
//               SPACE=&SRTEPSRP
//SORTWK03   DD   UNIT=&DISK,
//               SPACE=&SRTEPSRP
//SORTWK04   DD   UNIT=&DISK,
//               SPACE=&SRTEPSRP
//SORTWK05   DD   UNIT=&DISK,
//               SPACE=&SRTEPSRP
//SORTWK06   DD   UNIT=&DISK,
//               SPACE=&SRTEPSRP
//SORTWK07   DD   UNIT=&DISK,
//               SPACE=&SRTEPSRP
//SORTWK08   DD   UNIT=&DISK,
//               SPACE=&SRTEPSRP
//SORTWK09   DD   UNIT=&DISK,
//               SPACE=&SRTEPSRP
//SORTWK10   DD   UNIT=&DISK,
//               SPACE=&SRTEPSRP
//SORTWK11   DD   UNIT=&DISK,
//               SPACE=&SRTEPSRP
//SORTWK12   DD   UNIT=&DISK,
//               SPACE=&SRTEPSRP
//SORTWK13   DD   UNIT=&DISK,
//               SPACE=&SRTEPSRP
//SORTWK14   DD   UNIT=&DISK,
//               SPACE=&SRTEPSRP
//SORTWK15   DD   UNIT=&DISK,
//               SPACE=&SRTEPSRP
//SORTWK16   DD   UNIT=&DISK,
//               SPACE=&SRTEPSRP
//SORTWK17   DD   UNIT=&DISK,
//               SPACE=&SRTEPSRP
//SORTWK18   DD   UNIT=&DISK,
//               SPACE=&SRTEPSRP
//SORTWK19   DD   UNIT=&DISK,
//               SPACE=&SRTEPSRP
//SORTWK20   DD   UNIT=&DISK,
//               SPACE=&SRTEPSRP
//SORTIN     DD   DSN=&SYSTPFX..&RQ..HSTRPTI&OPNO..DATA,
//               DISP=(OLD,DELETE,KEEP)
//SORTOUT    DD   DSN=&SYSTPFX..&RQ..HSTRPTI&OPNO..SDATA,
//               DISP=(NEW,CATLG,DELETE),
//               DCB=*.SORTIN,
//               &DVCHRO
//SYSIN     DD   DSN=&LIBPFX..&PH..CNTL(SRHROD),

```

JHSTOX.TXT

```

//          DISP=SHR
//***** *****
//** PS035 - IEFBR14 DELETES THE WORK DSNS IN THE LOAD STEP      00098100
//***** *****
//** PS035 EXEC PGM=IEFBR14,                                         00098700
//          COND=(0,LT)
//** IN01    DD DSN=&SYSTPFX..&RQ..HSTRPTO&OPNO..DATA,           00098800
//          DISP=(MOD,DELETE,DELETE),
//          UNIT=SYSDA,
//          SPACE=(TRK,(1,1),RLSE)
//** IN02    DD DSN=&SYSTPFX..&RQ..OPPD&OPNO..DATA,             00104100
//          DISP=(MOD,DELETE,DELETE),
//          UNIT=SYSDA,
//          SPACE=(TRK,(1,1),RLSE)
//***** *****
//** SBHIST01 -
//***** *****
//PS040    EXEC PGM=IKJEFT01,
//          REGION=&SIZE,
//          COND=(0,NE)
//STEPLIB  DD DSN=&DB2REG..SDSNLOAD,
//          DISP=SHR
//          DD DSN=&LIBPFX..&PH..LOADLIB,
//          DISP=SHR
//SYSPRINT DD SYSOUT=&SYSOUT
//SYSUDUMP DD SYSOUT=&SYSOUT
//SYSABOUT DD SYSOUT=&SYSOUT
//SYSDBOUT DD SYSOUT=&SYSOUT
//SYSABEND DD SYSOUT=&SYSOUT
//SYSOUT   DD SYSOUT=&SYSOUT
//SYSTSPRT DD SYSOUT=&SYSOUT
//SYSTSIN  DD DSN=&LIBPFX..&PH..CNTL(&DB2REG),
//          DISP=SHR
//          DD DSN=&LIBPFX..&PH..CNTL(SBHIST01&OPNO.),
//          DISP=SHR
//HRODRIVE DD DSN=&SYSTPFX..&RQ..HSTRPTI&OPNO..SDATA,
//          DISP=SHR
//EPSOPU   DD DSN=&SYSTPFX..&RQ..SORTED.OPUPDT&OPNO.,
//          DISP=SHR
//HSTRPTO  DD DSN=&SYSTPFX..&RQ..HSTRPTO&OPNO..DATA,
//          DISP=(NEW,CATLG,DELETE),
//          DCB=(RECFM=FB,LRECL=37,BLKSIZE=0),
//          UNIT=&DISK,
//          SPACE=(CYL,(1,1),RLSE)
//WRKOPFL  DD DSN=&SYSTPFX..&RQ..OPPD&OPNO..DATA,
//          &WOPPDDSP,
//          DCB=(RECFM=FB,&ATRIPCLM),
//          &DVCWOPPD
//ERRORLOG DD SYSOUT=&SYSOUT
//***** *****
//** PS045 - IEFBR14 DELETES THE SORT OUT DSN      00098100
//***** *****
//** PS045 EXEC PGM=IEFBR14,                                         00098700
//          COND=(0,LT)
//** IN01    DD DSN=&SYSTPFX..&RQ..OPPD&OPNO..SDATA,           00098800
//          DISP=(MOD,DELETE,DELETE),
//          UNIT=SYSDA,
//          SPACE=(TRK,(1,1),RLSE)
//***** *****
//** SORT WRK_OP_PD X CLAIMS FILE
//***** *****
//PS050    EXEC PGM=SORT,
//          COND=(0,LT),

```

```

JHSTOX.TXT
//          PARM='CORE=MAX, RELEASE=ON, RLSOUT, SECOND=ON'
//SYSOUT    DD  SYSOUT=&SYSOUT
//SORTIN    DD  DSN=&SYSTPFX..&RQ..OPPD&OPNO..DATA,
//              DISP=SHR
//SRTWK01   DD  &SRTWOPPD
//SRTWK02   DD  &SRTWOPPD
//SRTWK03   DD  &SRTWOPPD
//SRTWK04   DD  &SRTWOPPD
//SRTWK05   DD  &SRTWOPPD
//SORTOUT   DD  DSN=&SYSTPFX..&RQ..OPPD&OPNO..SDATA,
//              DISP=(,CATLG,DELETE),
//              &DVCWOPPD
//SYSIN     DD  DSN=&LIBPFX..&PH..CNTL(CSRWKPD),
//              DISP=SHR
//*****                                                 *****
/*PS050      EXEC PGM=DSNUTILB,
/*          PARM='&DB2REG,&UID,&UTPROC1',
/*          REGION=&SIZE,
/*          COND=(0,LT)
/*STEPLIB   DD  DSN=&DB2REG..SDSNLOAD,
/*          DISP=SHR
/*SYSCOPY7  DD  DSN=&SYSTPFX..&RQ..IC.OPCLM&OPNO&GEN,
/*          DISP=(NEW,CATLG,DELETE),
/*          DCB=HMSADM.MODEL,
/*          UNIT=&TAPE,
/*          VOL=(,,255),
/*          RETPD=&RETPD
/*SYSPRINT  DD  SYSOUT=&SYSOUT
/*UTPRINT   DD  SYSOUT=&SYSOUT
/*SYSIN     DD  DSN=&LIBPFX..&PH..CNTL(&IC0CLM0),
/*          DISP=SHR
/*

```